

USB Drive Letter Change

In case your USB drives have taken over your main drive, you will need to change the letter of the USB drive. To accomplish this, follow the steps below.

1. Go to your Windows Start Menu (generally, in bottom left hand corner of your screen)
2. Click on and open the Control Panel option
3. Select Administrative Tools
4. Select Computer Management
5. From the menu on the left hand side, select Disk Management
6. At the top, click select top, then select Disk List
7. Right click on the drive you wish to alter, select change drive letter
8. Select change; select the new letter from the list.
9. Restart your computer